

BEADWORK

#CZ-SILKY-NT3-p

SILKY TAPERED NET

Triple & Double Bracelet pattern



SUPPLY LIST for DOUBLE 9 in.:

- 16 - 6mm 2-hole diagonal Silky beads
 - 18 - 6mm f/p crystals
 - 106 - 4mm 'O' beads
 - 186 - 8/ seed beads
 - 2-strand tubular clasp
- beading needle and thread
step-by-step instructions with **color photo** finish

SUPPLY LIST for TRIPLE 9 in.:

- 24 - 6mm 2-hole Silky beads
- 28 - 6mm f/p crystals
- 152 - 4mm 'O' beads
- 298 - 8/ seed beads
- 3 strand tubular clasp

This is a terrific opportunity to work with 2-hole Czech Silky beads, Os, new finishes on 6mm f/p crystals and Matubo seed beads. This modified netting technique has tapered ends attached to a tubular clasp for a comfortable fit. Choose to make a double or triple net. 2-hole Silky beads dictate thread path.

Maria M. Rypan is an international designer, instruction book publisher and educator since 1995. She is recognized for her Ukrainian style of beadwork and love of global folk arts.



Designed by Maria M. Rypan
for BeadSmith's Inspiration Squad

www.rypandesigns.com
416.247.1993

Pattern instructions published in Canada
No part of this instruction may be reproduced by any means without prior permission of RYPAN DESIGNS

BEADWORK

SILKY TAPERED NET BRACELET – 1/2

SILKY beads are 2-holed Czech pressed glass diagonal beads. The thread path is affected as you beadweave. Note tips!

Cut stringing material 2 yds.(2m) long
Tie a stopper bead with a 12" (30 cm) tail.

ROW 1: String 1C through hole, as shown. *fig.1*. Add 1D, 3A, 1D, 1B, 1D, 3A, 1D. String 1C in other direction, as shown. Repeat five (5) times. On sixth repeat, pass up through lowest C, as shown. *fig.2*


ROW 2: String 1D, 3A, 1D, 1B, 1D, 3A, 1D. Pass up through 2nd Silky hole, as shown. Repeat four (4) times. Remove stopper bead. Tie both strings in a double knot, as shown. *fig.3*. Pass down through the previous bead exiting D below crystal.

ROW 3: String 3A, 1D, 1C, 1D, 3A, 1D. Pass down through next 1D, 1B, 1D, as shown. Repeat four (4) times. To create the lower edge, string 3A, 1D, 1C, 1D, 3A, 1D, 1B, 3A, 1D. Pass up through 2nd Silky hole. *fig.4*

ROW 4: String 1D, 3A, 1D, 1B, 1D, 3A, 1D. Pass up through 2nd Silky hole, as shown. Repeat three (3) times. To create upper edge, string 1D, 3A, 1D, 1B, 1D, 3A, 1D, 1C, 1D, 3A. Pass down through the 1D, 1B crystal of previous row. *fig.5*. Continue down around and emerge to start Row 5. *fig.6*

ROW 5: String 3A, 1D, 1C, 1D, 3A. Pass up through next 1D, 1B, 1D crystal, as shown. Repeat four (4) times. *fig.7*

ROW 6: To create the upper edge, string 3A, 1D, 1C, 1D, 3A, 1D, 1B, 1D, 3A, 1D and pass down through 2nd Silky hole. Continue down around and up Row 5 to complete net. *fig.8*. See next page for net clasp attachment instructions.




Place in OPPOSITE direction

Maria M. Rypan ©2016 RYPAN DESIGNS, Toronto, CANADA

www.rypandesigns.com

No part of this instruction may be reproduced by any means without prior permission of RYPAN DESIGNS



BEADWORK

SILKY TAPERED NET BRACELET – 2/2

Choose how wide you want your bracelet: triple or double. All beads to taper each variation are drawn, but it is easier to study step photos for how to taper the ends and add tubular clasps.

TAPERED TRIPLE

TAPERING TRIPLE:

1. Start last row with 1D. Pass through end Sulky. String 1D, 1A, 1D. Pass through next 1C. Repeat step for Triple Net. Finish row with 1D. *Photo 1.*

2. String 5A and pass through single 1A between O beads and Sulky. Repeat step. String 5A again and pass through entire previous row and continue up through first three beads of the edge. *Photo 2.*

3. Sting 3A and pass through the centre of the previous string of beads. String 3A more and pass through the centre bead. Continue down other edge beads and through the inside of the tapered net to reinforce. *Photo 3.*

Taper the other end.

ADD CLASP:

4. Place the tubular clasp next to the tapered end. Align the middle loop with the centre bead of the edge. Pass through inside the edge and come out to catch the clasp loop from underneath. Go up loop and through a single seed. Repeat attaching clasp in the same direction for a professional finish. Continue inside for another round and reinforce clasp again. *Photo 4.*

5. Fold over clasp, as shown in *Photo 8*. Line up sliding portion of tubular clasp properly and attach clasp. Reinforce.




Photo 1



Photo 2



Photo 3



Photo 4

DOUBLE




Photo 5



Photo 6



Photo 7



Photo 8

TAPERING DOUBLE:

1. Start last row with 1D. Pass through end Silky. String 1D, 1A, 1D. Pass through next 1C. Finish row with 1D. *Photo 4.*

2. String 5A and pass through single 1A between O beads and Silkies. String 5A again and pass through the previous row. *Photo 5.*

3. Sting 3A and pass through the centre of the previous string of beads. Continue down other edge beads and through the inside of the tapered net to reinforce. *Photo 6.*

Taper the other end.

ADD CLASP:

4. Place the tubular clasp next to the tapered end. Align the loops with the centre bead of the edge. Pass through inside the edge and come out to catch the clasp loop from underneath. Go up loop and through a single seed. Continue inside for another round and reinforce clasp again. *Photo 7*

5. Fold over bracelet as shown. Line up the sliding portion of the tubular clasp properly. *Photo 8*

Start attaching the other side of the clasp from underneath, as shown.

Reinforce.



Maria M. Rypan ©2016 RYPAN DESIGNS, Toronto, CANADA

www.rypandesigns.com

No part of this instruction may be reproduced by any means without prior permission of RYPAN DESIGNS